

### MyTeams RFC

SPECIFICATIONS OF THE MYTEAMS COMMUNICATION PROTOCOL

Erwann WICART | Naïl PERREAU | Bradley MALBROUCK EPITECH, 2024

### **DEFINITIONS**

Here is a list of recurrent data types that will be used throughout this documentation.

Designation	Description	Type/Size	Additional information
Command code Command id	The command to execute on the server.	1-byte unsigned integer	See page X for the list of available commands.
Error code	An error code that is sent back and forth between the server and client.	1-byte unsigned integer	See page X for the list of possible errors.
UUID	Can be used to uniquely identify an item/user.	37 bytes ASCII characters	Composed of alphanumeric characters or '-'.
User name	The name of the user.	32 bytes ASCII characters	Composed of alphanumeric characters. Minimum 1 character. Case unsensitive.
Body size	The size of the data contained in this packet.	2-bytes unsigned integer	The size of the body does not include the size of the header.

### **REQUESTS**

#### **DESCRIPTION**

Every request is composed of two parts:

- The header: It contains information about the command to execute, the current user, the packed size etc...
- The body: it contains the actual data useful to the execution of the command on the server.

#### **MEMORY LAYOUT**

# Request (at least 41 bytes)

Header (41 bytes)

Body

#### **HEADER**

#### **DESCRIPTION**

The header contains 4 fields:

- The command code is the command to execute on the server. See page X for the list of available commands.
- An error code, used to pass error back and forth between the client and the server. For no error, set to o. See page X for the list of possible errors.
- The UUID of the user that initiated this request. See page X for more information about UUIDs.
- The size of the body. Set to o if the request only contains a header.

#### **MEMORY LAYOUT**

# Header (41 bytes)

Command id (1 byte) Error code (1 byte)

User UUID (37 bytes)

Body size (2 bytes)

### **COMMANDS**

#### Login

The login command allows a user to log in into its account. It takes one parameter, the username of the user to log in.

# Login Request

Header (41 bytes)

Body (32 bytes)

Command id (1 byte)

Error code (1 byte) User UUID (37 bytes) Body size (2 bytes)

User name (32 bytes)

Returns information about a user.

# User Request

Header (41 bytes)

Body (37 bytes)

Command id (1 byte) Error code (1 byte)

User UUID (37 bytes)

Body size (2 bytes)

User uuid (37 bytes)